

Key: AESExport\_DE\_IN\_XML\_AI  
XSD: interfaceDescription\_AESExport\_DE\_IN\_XML\_AI - Ausgang Ausfuhranmeldung - 1.1.0.xsd  
Document-Version: interfaceDescription\_AESExport\_DE\_IN\_XML\_AI - Ausgang Ausfuhranmeldung - 1.1.0  
Notes:

1	Root
1.1	Root.Client
1.2	Root.User
1.3	Root.CountryOfLodgement
1.4	Root.OperationDomain
1.5	Root.OperationType
1.6	Root.ID
1.7	Root.ReferenceNumber
1.8	Root.AdditionalReferenceNumber
1.9	Root.StatusNotificationEmail
1.10	Root.Meta
1.10.1	Root.Meta.Operation
1.10.2	Root.Meta.ReferenceType
1.11	Root.Transition
1.11.1	Root.Transition.TransitionType
1.11.2	Root.Transition.MRN
1.11.3	Root.Transition.EnquiryInformationCode
1.11.4	Root.Transition.ExitDate
1.11.5	Root.Transition.Text
1.11.6	Root.Transition.CustomsOfficeOfExport
1.11.7	Root.Transition.CustomsOfficeOfExitActual
1.11.8	Root.Transition.Declarant
1.11.8.1	Root.Transition.Declarant.Code
1.11.8.2	Root.Transition.Declarant.IdentificationNumber
1.11.8.3	Root.Transition.Declarant.SubsidiaryNumber
1.11.8.4	Root.Transition.Declarant.ContactPerson
1.11.8.4.1	Root.Transition.Declarant.ContactPerson.Name
1.11.8.4.2	Root.Transition.Declarant.ContactPerson.PhoneNumber
1.11.8.4.3	Root.Transition.Declarant.ContactPerson.EmailAddress
1.11.9	Root.Transition.Representative
1.11.9.1	Root.Transition.Representative.Code
1.11.9.2	Root.Transition.Representative.IdentificationNumber
1.11.9.3	Root.Transition.Representative.SubsidiaryNumber
1.11.10	Root.Transition.ExitCarrier
1.11.10.1	Root.Transition.ExitCarrier.Code
1.11.10.2	Root.Transition.ExitCarrier.IdentificationNumber
1.11.10.3	Root.Transition.ExitCarrier.SubsidiaryNumber
1.11.10.4	Root.Transition.ExitCarrier.Name
1.11.10.5	Root.Transition.ExitCarrier.Address
1.11.10.5.1	Root.Transition.ExitCarrier.Address.StreetAndNumber
1.11.10.5.2	Root.Transition.ExitCarrier.Address.Postcode
1.11.10.5.3	Root.Transition.ExitCarrier.Address.City
1.11.10.5.4	Root.Transition.ExitCarrier.Address.Country
1.11.11	Root.Transition.AlternativeEvidence
1.11.11.1	Root.Transition.AlternativeEvidence.Type
1.11.11.2	Root.Transition.AlternativeEvidence.TransportDocument
1.11.11.2.1	Root.Transition.AlternativeEvidence.TransportDocument.TypeAndQualifier
1.11.11.2.2	Root.Transition.AlternativeEvidence.TransportDocument.ReferenceNumber

Identifier	Required/ Optional	Format	Iteration
1 Root	K		1 - 1
1.1 Root.Client	K	..8	1 - 1
Client			
Identifier of the client where the operation is processed in AC.			
1.2 Root.User	O	..35	0 - 1
User			
AC-user under whose name the declaration is being imported and may be send to customs.			
1.3 Root.CountryOfLodgement	K	2	1 - 1
Country of lodgement			
ISO code of the country in which the operation is registered.			
Permitted values:			
DE	This import Interface may only be used for country of lodgement 'DE'		
1.4 Root.OperationDomain	K	..35	1 - 1
Operation domain			
Identifier for the process of the operation in AC. The country of lodgement, the operation domain and the operation type classify it.			
Permitted values:			
AES	Operation domain 'AES'		
1.5 Root.OperationType	K	..50	1 - 1
Operation type			
Identifier for the operation.			
Permitted values:			
Ausgang zur Ausfuhr	Operation type 'Ausgang zur Ausfuhr'		
1.6 Root.ID	O	..	0 - 1
ID			
For updating processes: ID is the transaction number created by AC after a transaction is registered. If the declaration is to be updated via the interface by ID, the field is allowed to be sent.			
1.7 Root.ReferenceNumber	O	..50	0 - 1
Reference number			
The reference number is the internal reference number of the declaration.			
This number needs to be unique for all processes of the same classification (Combination of country of lodgement, operation domain and operation type).			
1.8 Root.AdditionalReferenceNumber	O	..50	0 - 1
Additional reference number			
An additional reference number that can be used for the technical identification of the transaction. (not mandatory)			
1.9 Root.StatusNotificationEmail	O	..255	0 - 1
Status notification			
Use of the e-mail function in Advantage Customs is required. An email address is provided that is used for status notifications for the customs declaration. The configured e-mail settings in Advantage Customs are considered.			
1.10 Root.Meta	K		1 - 1
Meta			
The following elements define the processing of the transaction.			
1.10.1 Root.Meta.Operation	K	..	1 - 1
Operation			
Specification of the processing in AC.			
Permitted values:			
0	simulation of an import including validation (nothing will be stored in AC)		
1	import of the operation into AC without business validation and dispatch		
5	import of the operation into AC including business validation and dispatch (in case of validation errors the operation will still be stored in AC)		
7	import of the operation into AC including business validation and dispatch (in case of validation errors the operation will NOT be stored in AC)		

Identifier		Required/Optional	Format	Iteration
<b>1.10.2 Root.Meta.ReferenceType</b>		0	..35	0 - 1
Reference type  For updating processes: The reference type controls the update logic of the interface: If the element 'Root/ReferenceType' is not transmitted in the data set, it is always a new creation. If a reference type is transmitted, it is an update data set. The specified value controls which reference is used to determine the transaction to be updated in AC.  The supported reference types are 'ID' and 'ReferenceNumber'.  Permitted values:				
ID	ID Referencing via the unique technical ID of the transaction. The ID is assigned by AC when a new transaction is created. In order to control updates from the customer's system via this ID, the system must receive and save the ID (e.g. via receipt or export interfaces).			
ReferenceNumber	Reference number Referencing via the reference number of the transaction.			
<b>1.11 Root.Transition</b>		K		1 - 1
Transition  Field which AC internally uses to identify the current type of transition. Usually it correlates to the type/name of the exchanged message.				
<b>1.11.1 Root.Transition.TransitionType</b>		K	9	1 - 1
Transition type  Indication of the ATLAS message.  Permitted values:				
E_EXP_EXT	The ATLAS message type must always be E_EXP_EXT.			
<b>1.11.2 Root.Transition.MRN</b>		0	18	0 - 1
MRN  Indication of the Master Reference Number (MRN)				
<b>1.11.3 Root.Transition.EnquiryInformationCode</b>		0	..	0 - 1
Enquiry information code  ATLAS code list: S0210  Indication of the enquiry information code.  Note: Content of the code list:  2 = delayed exit  4= exit occurred, alternative evidence existing				
<b>1.11.4 Root.Transition.ExitDate</b>		0	..	0 - 1
Exit date  Date of the actual or scheduled exit				
<b>1.11.5 Root.Transition.Text</b>		0	..512	0 - 1
Text  Notes of the participant				
<b>1.11.6 Root.Transition.CustomsOfficeOfExport</b>		0	8	0 - 1
Customs office of export  ATLAS code list: D0293  Reference number of the customs office of export				
<b>1.11.7 Root.Transition.CustomsOfficeOfExitActual</b>		0	8	0 - 1
Customs office of exit (actual)  ATLAS code list: C0194  Reference number of the customs office of exit (actual)				
<b>1.11.8 Root.Transition.Declarant</b>		0		0 - 1
Declarant				
<b>1.11.8.1 Root.Transition.Declarant.Code</b>		0	..250	0 - 1
Code  The reference code for the business partner master data in AC.				

Identifier	Required/Optional	Format	Iteration
<b>1.11.8.2 Root.Transition.Declarant.IdentificationNumber</b>	0	..17	0 - 1
Identification number			
Indentification number / EORI number			
<b>1.11.8.3 Root.Transition.Declarant.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number			
Number of the subsidiary of the sub-contractor assigned by the German customs authority.			
<b>1.11.8.4 Root.Transition.Declarant.ContactPerson</b>	0		0 - 1
Contact person of the declarant			
<b>1.11.8.4.1 Root.Transition.Declarant.ContactPerson.Name</b>	0	..70	0 - 1
Name of the contact person of the declarant			
<b>1.11.8.4.2 Root.Transition.Declarant.ContactPerson.PhoneNumber</b>	0	..35	0 - 1
Phone number of the contact person of the declarant			
<b>1.11.8.4.3 Root.Transition.Declarant.ContactPerson.EMailAddress</b>	0	..256	0 - 1
E-mail address of the contact person of the declarant			
<b>1.11.9 Root.Transition.Representative</b>	0		0 - 1
Representative			
<b>1.11.9.1 Root.Transition.Representative.Code</b>	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
<b>1.11.9.2 Root.Transition.Representative.IdentificationNumber</b>	0	..17	0 - 1
Identification number			
Indentification number / EORI number			
<b>1.11.9.3 Root.Transition.Representative.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number			
Number of the subsidiary of the representative assigned by the German customs authority.			
<b>1.11.10 Root.Transition.ExitCarrier</b>	0		0 - 1
Exit carrier			
<b>1.11.10.1 Root.Transition.ExitCarrier.Code</b>	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
<b>1.11.10.2 Root.Transition.ExitCarrier.IdentificationNumber</b>	0	..17	0 - 1
Identification number			
Indentification number / EORI number			
<b>1.11.10.3 Root.Transition.ExitCarrier.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number			
Number of the subsidiary of the exit carrier assigned by the German customs authority.			
<b>1.11.10.4 Root.Transition.ExitCarrier.Name</b>	0	..70	0 - 1
Name			
Name or company name of the exit carrier			
<b>1.11.10.5 Root.Transition.ExitCarrier.Address</b>	0		0 - 1
Address			
Address data of the exit carrier			
<b>1.11.10.5.1 Root.Transition.ExitCarrier.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.10.5.2 Root.Transition.ExitCarrier.Address.Postcode</b>	0	..17	0 - 1
Postcode			
<b>1.11.10.5.3 Root.Transition.ExitCarrier.Address.City</b>	0	..35	0 - 1
City			

Identifier	Required/Optional	Format	Iteration
<b>1.11.10.5.4 Root.Transition.ExitCarrier.Address.Country</b>	0	2	0 - 1
Country			
ATLAS code list: C0248			
Country Code			
<b>1.11.11 Root.Transition.AlternativeEvidence</b>	0		0 - 9
Alternative evidence			
<b>1.11.11.1 Root.Transition.AlternativeEvidence.Type</b>	0	..	0 - 1
Type			
ATLAS code list: S0170			
Type of alternative evidence			
<b>1.11.11.2 Root.Transition.AlternativeEvidence.TransportDocument</b>	0		0 - 99
Transport document			
<b>1.11.11.2.1 Root.Transition.AlternativeEvidence.TransportDocument.TypeAndQualifier</b>	0	..8	0 - 1
Type and qualifier			
ATLAS code list: IO941			
Type and Qualifier of transport document			
<b>1.11.11.2.2 Root.Transition.AlternativeEvidence.TransportDocument.ReferenceNumber</b>	0	..70	0 - 1
Reference number			
Reference number of transport document			